

How to use monitors to track endpoint performance

Click 'Applications' > 'Endpoint Manager' > 'Configuration Templates' > 'Monitors'

- A monitor is a script that tracks the activity on a managed endpoint and alerts you if its conditions are met.
- For example, you could create a monitor that alerts you if CPU usage goes above 75% for a certain length of time.
- You add the monitor to a configuration profile which is in-turn applied to your devices.
- A single monitor can be used in multiple profiles. A single profile can include any number of monitors.
- Endpoint Manager ships with a set of canned monitors that you can quickly deploy. You can also create custom monitors to track items of your choice.
- You can create new monitors from scratch, or clone an existing monitor then edit it as required.


This article explains how to create a monitor, add it to a profile, and view monitor logs.

- [The monitors area](#)
 - [Create a new monitor](#)
 - [General Settings](#)
 - [Choose what to monitor](#)
 - [Conditions and thresholds](#)
 - [Optional - Add a custom script to the monitor](#)
 - [Optional - Add variables to your custom script](#)
 - [Clone an existing monitor and edit it as required](#)
- [Add a monitor to a profile](#)
- [View monitor logs](#)

The monitors area

- Login to Comodo One / Dragon
- Click 'Applications' > 'Endpoint Manager'
- Click 'Configuration Templates' > 'Monitors'





There are two types of monitor:

- **Predefined Monitors** - A collection of monitors from Comodo which perform a range of useful monitoring tasks. These can be used in custom profiles, but cannot be edited.
- **My Monitors** - Custom monitors that you create. These monitors are saved in the 'My Monitors' folder. You can add custom sub-folders as required.

There are two ways to add custom monitors:

- [Create a new monitor from scratch](#)
- [Clone a monitor then edit it as required](#)

Create a new monitor from scratch

- Click 'Configuration Templates' > 'Monitors'
- Click 'Create Monitor'



The screenshot shows the 'Monitors' management interface. On the left is a folder tree under 'My Monitors'. The main area has three buttons: 'Create Monitor', 'Clone Monitor', and 'Delete Monitor'. The 'Create Monitor' button is circled in red, and a red arrow points from it to a 'Create monitor' dialog box. The dialog box has a blue header with a close button. It contains the following fields:

- Monitor name ***: A text input field with the placeholder 'Monitor name'.
- OS**: A dropdown menu currently showing 'Windows'.
- Description**: A large text area for entering a description.
- Folder ***: A dropdown menu currently showing 'My Monitors'.
- Create**: A blue button at the bottom right.

General Settings

- Enter a label and description for the monitor
- Select the operating system of the target device. Supported operating systems are Windows and Mac OS.
- Specify where to save the new monitor. You can create new sub-folders under 'My Monitors' if required.
- Click 'Create'.
- This opens the monitor configuration screen:



The screenshot shows a configuration form for a monitor titled "Finance Department Mac Computers". The form has four tabs: "General", "Conditions", "Profiles", and "Logs". Callout boxes provide instructions for each tab:

- General:** Edit name, description, folder and alert settings.
- Conditions:** Select the parameters to be monitored and configure thresholds.
- Profiles:** View the configuration profiles to which the monitor is added.
- Logs:** View logs of events related to the monitor.

 The form fields are:

- Monitor name ***: Finance Department Mac Computers
- Description**: Observe performance of Mac computers in Finance Dept
- Folder**: Finance Department Windows Computers
- Trigger an alert if**: All of the conditions are met
- Use alert settings**: Default Alert

 Buttons for "Cancel" and "Save" are visible in the top right corner.

Modify the following settings if required:

Trigger an alert if - Select when admins should receive an alert. The options are (i) when all monitored conditions are met, or (ii) when any monitored condition is met.

Use Alert Settings - Choose the alert template. The alert template is a collection of settings that determine additional recipients and other settings.

- The 'Default Alert' template is a good starting point. It sends email alerts to admins and creates notifications in the portal itself.
- You can configure your own alert template at 'Configuration Templates' > 'Alerts'.
- See [this page](#) if you want more help to configure an alert template.

Auto Remediation on alert - *Windows only*. Choose how you want to respond to the alert:


- **Taken no action** - No automatic response is made to the alert. You can, of course, manually run a procedure in response to the alert.
- **Run below procedure** - Select a procedure to run on affected endpoints in response to the alert.

- The procedures listed here are defined in the 'Configuration Templates' > 'Procedures' interface.
- Type the first few characters of the procedure and select from the list.
- See [this page](#) if you want more help with procedures

- Click 'Save'

Choose what to monitor

- Click 'Add Condition'



Choose the item you want to monitor:

- **Performance** - Checks CPU, RAM, Network and Disk usage. You are alerted if usage goes above (or below) a certain threshold.
- **Disk** - Checks free disk space and for large changes to free disk space in short periods, on system drive and other disk drives / partitions.

Triggers an alert if free disk space in any of the system drive or other drive partitions falls below a certain level, or if there are large alterations to disk space in a short time.

- **Process** - Checks whether or not a named process is running.
- **Device Status** - Checks every managed device to see whether it has been online or offline for a certain length of time.
 - Background. Every minute, managed devices send a message to Endpoint Manager to signal that they are online. If EM does not receive this signal for three minutes then the device status is set to 'Offline'. You will get an alert you if a device has been continuously 'Offline' (or 'Online') for the length of time you specify.

The following additional monitors are *only* available for Windows:

- **File Size** - Checks the disk space used by a specific file. Triggers an alert if the file is larger or smaller than the size you specify.
- **Folder Size** - Checks the disk space used by a directory. Triggers an alert if the folder is larger or

smaller than the size you specify.

- **Service** - Checks whether or not a named service is running. Triggers an alert if the condition is met.
- **Event** - Checks if a specific event occurs and alerts you accordingly. You must specify the event ID, the criticality of the event, and the source of the event. The monitor checks Windows event logs for the information you enter.
- **TCP** - Checks whether a specific port is open or closed and alerts you accordingly. This is useful for important ports that need to remain open/closed for operational reasons.

You need to specify the hostname/ IP of the target port, the port number, the polling interval (in seconds), and whether you want to test for an open or closed state.

- **Ping** - Checks whether a host is online or not. You need to specify the hostname, fully qualified domain name (FQDN) or IP of the host, the polling interval (in seconds), and whether you want to test for online or offline status.
- **Web Page** - Checks whether specific content is present or not present on a web-page. You need to specify the URL, the text you want to search for and the polling interval (in minutes). You are alerted if the condition is met.
- **Custom Script** - Create a python script to monitor for your own set of conditions. Paste your script in the space provided. See [Add a custom script to the monitoring condition](#) if you need help with this.
- **Security Events** - Checks for significant security-related events on the managed endpoint. Example events:

- Malware detected and handled
- Malware detected and not handled
- Unknown application is placed in the container
- An external device was blocked by the device control

You can receive an alert when the condition is met, or automatically run a procedure.

- **Security Client Events** - Alerts you when there are errors with Comodo Client Security (CCS).

CCS is the endpoint application that provides the antivirus, firewall and containment services. This monitor checks for any failure in those processes, including:

- Antivirus scan failed or interrupted
- Antivirus database update failed
- Antivirus scan interrupted
- Another antivirus is installed

You can receive an alert when the condition is met, or automatically run a procedure.

• **OS Patches Event** - Alerts you when various types of Windows patch are installed. You can monitor the installation of:

- Critical Updates
- Definition Updates
- Upgrades
- Feature Packs
- Update Rollups
- Service Packs
- Tools
- Updates
- Security updates

Conditions and thresholds

After choosing the items you want to monitor, you can define the conditions upon which you receive an alert. The type of information you need to provide depends on the item monitored. For example, if you select 'Disk', you can specify conditions for one of three values:

Add Condition for «Disk»

Parameter

- Free space left on the system drive
- Free space left on all the drives
- Free space change on the system drive

Condition **Value ***

Less than 10 %

Note:
The monitor checks the amount of free space on the selected drive(s) and triggers an alert if the specified conditions are met.

Create

- Click 'Create' after specifying the conditions.
- Repeat the process to add more conditions



Finance Department Mac Computers Cancel Save

General **Conditions** Profiles Logs

Add Condition Remove Condition

<input type="checkbox"/>	TYPE	TARGET	CONDITIONS
<input type="checkbox"/>	CPU usage		More than 50% for 1 min
<input type="checkbox"/>	Free space left on the system drive		Less than 50%
<input type="checkbox"/>	Online / offline		Device is offline during 30 min

- Click 'Save' to apply your changes. Repeat the process to create more monitors.
- Next: You have the option to add custom scripts and/or variables or skip to [Add the monitor to a profile](#).

Optional - Add a custom script to the monitor

You can create custom scripts in python and define which items should be monitored. You can also define the threshold before an alert is generated.

You can also add dynamic variables to the script. Values for the variables are fetched at run time.

- Choose 'Custom script' from the 'Add Condition' drop-down



Add Condition for «Custom script»



Name *

Description

Check Period

min

Trigger monitoring alert if custom script failed

Triggering Method

By status

Note:

- This monitor will be triggered if actual status is ON
- Please write your code on below box to create your own custom script condition.
- Please use "alert(1)" to turn on the condition (trigger an alert) and "alert(0)" to turn off the condition (disable an alert).
- Please define the custom alert text inside the code with "Print" function



Add Existing Procedure



Undo



Redo

```
1 # The script is a template to check UAC status on device.
2 import os
3 import sys
4 import _winreg
5
6 def alert(arg):
7     sys.stderr.write("%d%d%d" % (arg, arg, arg))
8
9 # Please use "alert(1)" to turn on the monitor(trigger an alert)
10 # Please use "alert(0)" to turn off the monitor(disable an alert)
11 # Please do not change above block and write your script below
12
13 def checkUAC():
14     if 'PROGRAMW6432' in os.environ.keys():
15
```

Create

- **Name** - Create a label that identifies the purpose of the script.
- **Description** - Enter a short description of the script.
- **Check Period** - The time interval at which the script should run on the device. Ensure the check period is greater than the time taken for the script to run, so there is no overlap in successive executions.
- **Trigger monitoring alert if custom script failed** - Select if you want to be notified if the script did not run successfully.

- **Triggering Methods** - The new monitor triggering method generates an alert while the conditions are changed even when the monitor is 'ON' state. The users will be able to use this triggering method for getting alerts while their monitor is still on 'ON' state. Admin should be able to choose the following custom script monitoring triggering methods.
 - **By status** - The monitor will be triggered if the actual status is ON
 - **By status changing** - The monitor will be triggered if the status is changed from OFF to ON.
- **Script** - Enter your Python script in the text editor.

Note 1: Keep the following lines intact in the editor and enter your script below these:

```

1 # The script is a template to check UAC status on device.
2 import os
3 import sys
4 import _winreg
5 |
6 def alert(arg):
7     sys.stderr.write("%d%d%d" % (arg, arg, arg))
8
9 # Please use "alert(1)" to turn on the monitor(trigger an alert)
10 # Please use "alert(0)" to turn off the monitor(disable an alert)
11 # Please do not change above block and write your script below

```

Note 2: If you want an alert to be triggered if the condition is met set the argument to alert parameter to 1, i.e. 'alert(1)'.

If you do not want an alert to be triggered even if the condition is met set the argument to alert parameter to 0, i.e. 'alert(0)'.

Note 3: You can import an existing script procedure in EM if you wish to create a new custom monitor script using an existing procedure as a starting point. Python script monitors by the Comodo One / Dragon development team are available in the 'Monitors' folder under 'Configuration Templates' > 'Procedures' > 'Predefined Procedures'.

- Click 'Add Existing Procedure' and choose the existing procedure.
- Edit the script as per your requirement as per Note 1.
- See [this page](#) for more details on procedures.

Note 4: In addition to the above, Comodo One / Dragon hosts a plethora of scripts at <https://scripts.comodo.com>. Feel free to download python scripts for use here. If you require custom scripts from Comodo One / Dragon, please raise a request at <https://forum.comodo.com/forum/general-discussions/request-a-script>

Note 5: You can add variable parameters to your custom scripts. The values for the parameters are fetched at run time. [Click here](#) to know-how.

- Click 'Create'


- Next: [Add the monitor to a profile.](#)

Optional - Add variables to your custom script

You can include variables whose values are dynamically populated when the monitor runs.


- Click 'Configuration Templates' > 'Monitors'
- Click 'Create Monitors'
- Complete the form as explained above.
- Click 'Add Condition' and select 'Custom script'
- See 'Add Custom Monitoring Conditions' [explained above.](#)
- Scroll down to the script area and enter the following code:

```
name=itsm.getParameter('parameterName')
```



- Repeat the process to add more parameters
- Complete the script and click 'Create'

Custom script parameters dialogue box appears:



- **Type** - Select the parameter type from the drop-down. Available types are:

Integer

Float

Unicode

List

- **Value** - Enter the appropriate parameter value.

- Click 'Save'

Create a new monitor by cloning an existing monitor

- Cloning a monitor then modifying it is an easy way to create a custom monitor.

Clone a monitor

- Click 'Configuration Templates' > 'Monitors'
- Browse the folder tree on the left and locate the monitor you want to clone
- Select the source monitor then click 'Clone Monitor':



The screenshot shows the 'Monitors' management interface. On the left is a sidebar with a search bar and a tree view of folders including 'My Monitors', 'Default', 'Finance Department Wi...', 'Monitoring Important D...', 'Sales Dept Monitors', 'Suspicious Files Folder ...', and 'Predefined Monitors'. The main area displays a table of monitors with columns for OS, Monitor Name, Type, # of Profiles, and Created By. The 'Clone Monitor' button is circled in red, and a red arrow points to a 'Clone monitor' dialog box. The dialog box has a title bar with a close button and contains the following fields:

OS	MONITOR NAME	TYPE	# OF PROFILES	CREATED BY
<input type="checkbox"/>	Finance Department...	Custom	1	herculespopul...
<input checked="" type="checkbox"/>	Finance Department...	Custom	0	herculespopul...
<input type="checkbox"/>	Stas of Mac OS D...	Custom	1	herculespopul...

Clone monitor [X]

Monitor name *
[Cloned] Finance Department Windows Computers

Description
[Empty text area]

Folder *
My Monitors

[Clone]

- Change the name, if required, and provide an appropriate description.
- Select the folder where you want to save the monitor. You can create new sub-folders under 'My Monitors' if required.
- Click 'Clone'

Next, we move onto the monitor configuration screen:



Finance Department Windows Computers - 2
Cancel Save

General Conditions Profiles Logs

Monitor name *

Description

Folder

Trigger an alert if

All of the conditions are met
▼

Use alert settings

Auto remediation on alert

Take no action

Run below procedure

Update the parameters of the monitor as required. All settings are explained in the new monitor section [above](#).

Add a monitor to a profile

- Log into Comodo One / Dragon
- Click 'Applications' > 'Endpoint Manager'
- Click 'Configuration Templates' > 'Profiles'
- Open the profile applied to your target devices
 - Open the 'Monitors' tab
- OR
- Click 'Add Profile Section' > 'Monitors', if you haven't yet added the section
- Click 'Add Monitor'



Finance Dept Mac Devices

Add Profile Section Export Profile Clone Profile Delete Profile Make Default

General **Monitors**

Add Monitor Remove Monitor

<input type="checkbox"/>	MONITOR NAME	TYPE	CREATED BY	CREATED ON	LAST MODIFIED BY	UPDATED ON
No results found.						

Add Monitor

Choose Monitor(s) *

Type approved monitor name to search among monitors

To create new monitors, go to [Monitors](#) page.

OK

Choose Monitor(s) - Add monitors to the profile. Type the first few letters of a monitor name and select from the suggestions.

- Repeat the process to add more monitors to the profile
- Click 'OK' to add the monitors

The monitors screen shows all monitors added to the profile:



Finance Dept Mac Devices						
Add Profile Section Export Profile Clone Profile Delete Profile Make Default						
General Monitors						
Add Monitor Remove Monitor Refresh Filter						
<input type="checkbox"/>	MONITOR NAME	TYPE	CREATED BY	CREATED ON	LAST MODIFIED BY	UPDATED ON
<input type="checkbox"/>	Finance Departm...	Custom	herculespopular22@gmail.com	2019/11/19 01:52:54 PM	herculespopular22@gmail.com	2019/11/19 02:07:46 PM
<input type="checkbox"/>	CPU	Custom	herculespopular22@gmail.com	2019/11/18 03:29:16 PM	Never modified	Never modified

The monitors will be implemented on devices during the next sync. You will receive alerts whenever the conditions of a monitor are met.

View monitor logs

- Log into Comodo One / Dragon
- Click 'Applications' > 'Endpoint Manager'
- Click 'Configuration Templates' > 'Monitors'
- Click the name of a monitor to open its details screen
- Click the 'Logs' tab.

The logs tab shows all instances where the conditions of the monitor were breached:






Finance Dept Mac Devices Edit Delete

General Conditions Profiles **Logs**

comodo's Mac mini - Log Details ← Back

Logs Tickets Statuses

TIME	STATUS	ADDITIONAL INFORMATION
2019/11/28 04:59:24 PM	OFF	CPU Monitor : Threshold is More than 5% - usage is 10% during 60s 
2019/11/28 04:59:24 PM	OFF	CPU Monitor : Threshold is More than 5% - usage is 10% during 60s 
2019/11/28 01:59:47 PM	OFF	CPU Monitor : Threshold is More than 5% - usage is 9% during 60s 

Details are shown in three tabs:

1) **Logs** - Date and time the event occurred, the condition that was broken.

- **Time** - Date and time of the event.
- **Status** - Shows whether or not the device is currently exceeding the monitored condition.
 - On** - The device is currently exceeding the thresholds of the monitor
 - Off** - The device is currently operating within the thresholds of the monitor
- **Additional Information** - Details on the condition monitored and the breach

2) **Tickets** - Shows service desk tickets which were auto-generated in response to the breached condition:

comodo's Mac mini - Log Details ← Back


Logs **Tickets** Statuses

LINK	STATUS	CREATED ON
https://frontfork.staging.servicedesk.comodo.com/scp/tickets.php?id=1062	Open	2018/12/31 04:14:15 PM
https://frontfork.staging.servicedesk.comodo.com/scp/tickets.php?id=1062	Open	2018/12/31 03:37:35 PM

- **Link** - A link to the support ticket created for the breach event.
- **Status** - Shows whether the ticket is open or closed


- **Created On** - The date and time at which the ticket was created.

3) Statuses:



CONDITION TYPE	VALUE	STATUS	STATUS CHANGED AT
CPU usage	More than 5% for 1 min	●	2019/11/28 04:59:24 PM
Free space left on the syst...	Less than 80%	●	Not modified
RAM usage	More than 10% for 1 min	●	2019/11/28 04:59:24 PM

- **Condition Type** - The category of the monitor. Click the type to view its exact conditions and thresholds. An example is shown below:



Parameter	Condition	Value	During
CPU usage	More than	5%	1 min

Note
The monitor checks the computer performance metrics. If the selected parameter meets the specified condition, the monitor triggers an alert.

- **Value** - The thresholds set for the parameter.
- **Status** - The current state of the monitored parameter on the device.
 - Green - The device is operating within the thresholds of the monitor
 - Grey - Unknown
 - Red - The device is exceeding the conditions of the monitor.
- **Status Changed at** - The date and time of the most recent change to the monitored parameter.