

# How to configure User Access Rights Verification in Xcitium Client Security

Use the following links to jump to the task you need help with:

- [Introduction](#)
- [User Access Rights Verification](#)
- [Setting the User Access Rights Verification](#)
  - [Xcitium dialog box](#)
  - [Windows UAC](#)

## Introduction


Some features of **Xcitium** Client Security requires elevated rights to perform certain actions. To perform these actions current users need to prove that they have sufficient rights to do so.

The admin or technician can set User Access Rights Verification to validate other user actions. To configure this User Access Rights Verification, please follow the below steps

### User Access Rights Verification:

Go to **Xcitium** Client Security > Settings > General Settings > User Interface. In this section, the Admin or Technician user can configure user access rights verification.

This "User Access Rights Verification " prompts the end-user to provide the user access rights to perform certain actions on **Xcitium** Client Security




## Setting the User Access Rights Verification

The Admin or Technician user can select the type of access rights verification based on his choice.


They are

1. [Xcitium dialog box](#)
2. [Windows UAC](#)



## Step [a]: Selecting Xcitium dialog box

Select this "Xcitium dialog" option from the drop-down and then click "Ok".




Now the "Xcitium dialog" is enabled as User access rights verification. When a user tries to perform some actions on Xcitium Client Security, it prompts a Xcitium dialog box to the current user at his endpoint. After entering the password by the current user, then only the user can perform his action on Xcitium Client Security.

### For Example:

If a user wants to make changes in containment settings, then a Xcitium dialog box is prompted at the current user's endpoint requires verification from that user.

A sample screenshot is given below




**Note:**

You can configure password for **Xcitium** Client Security from Endpoint Manager> ‘Configuration Templates’ > ‘Profiles’ > click the name of a Windows profile > 'Add Profile Section' > 'Client Access Control. See [this wiki](#) to know more.

**Step [b]: Selecting Windows UAC**

Select this "Windows UAC" option from the drop-down and then click “Ok”.



Now the "Windows UAC" is enabled as User access rights verification. When a user tries to perform some actions on **Xcitium** Client Security, it prompts a Windows UAC access to the current user at his endpoint. After providing access by the current user, then only the user can perform his action on **Xcitium** Client Security.

**For Example:**

If a user wants to enable or disable the HIPS of an end user. Then the "Windows UAC" access is prompted at the current user’s endpoint requires verification from that user.

A sample screenshot is given below

